

EMULEX
VAX DIAGNOSTICS
INSTALLATION AND USER'S GUIDE

DIAGNOSTIC MONITOR AND VERSION:	VAX-11/780: ESSAA Version 6.0 or later VAX-11/750: ECSAA Version 6.0 or later VAX-11/730: ENSAA Version 6.0 or later
EMULEX SOFTWARE VERSION:	VAX-DISK FORMATTER Version 2.0 VAX-DISK-EXERCISER Version 1.2 SC21 DIAGNOSTIC Version 1.6 TC11 DIAGNOSTIC Version 1.2 CS11 DIAGNOSTIC Version 1.1
EMULEX DISTRIBUTION MEDIA:	VX9960401 Cartridge VX9960501 Floppy Disk



3545 Harbor Boulevard
Costa Mesa, California 92626
(714) 557-7580 TWX 910-595-2521

VX9951001 Rev B
December, 1983

Copyright (C) 1983 by Emulex Corporation

The information in this manual is for informational purposes and is subject to change without notice.

Emulex Corporation assumes no responsibility for any errors which may appear in the manual.

Printed in U.S.A.

TABLE OF CONTENTS

Section	Page
1	VAX-DISK-FORMATTER
1.1	GENERAL DESCRIPTION
1.2	REQUIREMENTS
1.2.1	Hardware Requirements
1.2.2	Software Requirements
1.3	LOADING PROCEDURES
1.3.1	Copying the Files Onto the System Disk
1.3.2	Starting the Diagnostic Supervisor
	-- VAX-11/780
1.3.2.1	Starting the Diagnostic Supervisor
	(Off-Line)
1.3.3	Operating Procedures for the VAX-11/780
1.3.4	Starting the Diagnostic Supervisor
	-- VAX-11/750
1.3.4.1	Starting the Diagnostic Supervisor
	(Off-Line)
1.3.5	Operating Procedures for the VAX-11/750
1.3.6	Starting the Diagnostic Supervisor
	-- VAX-11/730
1.3.6.1	Starting the Diagnostic Supervisor
	(Off Line)
1.3.7	Operating Procedures for the VAX-11/730
1.4	PROGRAM DESCRIPTION
1.4.1	Help Section
1.4.2	Forver Section
1.4.3	Verify Section
1.4.4	Readall Section
1.4.5	Update Section
1.4.6	Rebuild Section
1.4.7	Display Section
1.5	PROGRAM OPTIONS
1.6	DISTRIBUTION
2	VAX-DISK-EXERCISER
2.1	GENERAL DESCRIPTION
2.2	REQUIREMENTS
2.2.1	Hardware Requirements
2.2.2	Software Requirements
2.3	LOADING PROCEDURES
2.3.1	Copying the Files Onto the System Disk
2.3.2	Starting the Diagnostic Supervisor
	-- VAX-11/780
2.3.2.1	Starting the Diagnostic Supervisor
	(Off-Line)
2.3.3	Operating Procedures for the VAX-11/780
2.3.4	Starting the Diagnostic Supervisor
	-- VAX-11/750

TABLE OF CONTENTS (continued)

Section	Page
2.3.4.1 Starting the Diagnostic Supervisor (Off-Line)	2-4
2.3.5 Operating Procedures for the VAX-11/750	2-5
2.3.6 Starting the Diagnostic Supervisor -- VAX-11/730	2-6
2.3.6.1 Starting the Diagnostic Supervisor (Off-Line)	2-6
2.3.7 Operating Procedures for the VAX-11/730	2-6
2.4 PROGRAM DESCRIPTION	2-7
2.4.1 Default Section	2-8
2.4.2 Qualification Section	2-8
2.4.3 Seek Timing Section	2-8
2.4.4 Media Section	2-8
2.4.5 Multi-Drive Section	2-9
2.5 DISTRIBUTION	2-9
 3 SC21 DIAGNOSTIC	 3-1
3.1 GENERAL DESCRIPTION	3-1
3.2 REQUIREMENTS	3-1
3.2.1 Hardware Requirements	3-1
3.2.2 Software Requirements	3-1
3.3 LOADING PROCEDURES	3-1
3.3.1 Loading Procedures for the VAX-11/780	3-1
3.3.2 Loading Procedures for the VAX-11/750	3-2
3.3.3 Loading Procedures for the VAX-11/730	3-2
3.4 PROGRAM DESCRIPTION	3-5
3.4.1 Default Section	3-5
3.4.2 Configuration Section	3-5
3.5 DISTRIBUTION	3-6
3.6 MAINTENANCE HISTORY	3-7
 4 TC11 DIAGNOSTIC	 4-1
4.1 GENERAL DESCRIPTION	4-1
4.2 REQUIREMENTS	4-1
4.2.1 Hardware Requirements	4-1
4.2.2 Software Requirements	4-1
4.3 LOADING PROCEDURES	4-1
4.3.1 Loading Procedures for the VAX-11/780	4-1
4.3.2 Loading Procedures for the VAX-11/750	4-2
4.3.3 Loading Procedures for the VAX-11/730	4-2
4.4 PROGRAM DESCRIPTION	4-4
4.4.1 Default Section	4-4
4.4.2 Configuration Section	4-5
4.4.3 PE Section	4-5
4.4.4 Tape Section	4-6
4.4.5 Manual Section	4-6
4.5 ERROR AND INFORMATION MESSAGES	4-7
4.6 DISTRIBUTION	4-7

TABLE OF CONTENTS (continued)

Section		Page
4.7	MAINTENANCE HISTORY	4-8
5	CS11 DIAGNOSTICS	5-1
5.1	GENERAL DESCRIPTION	5-1
5.2	REQUIREMENTS	5-1
5.2.1	Hardware Requirements	5-1
5.2.2	Software Requirements	5-1
5.3	LOADING PROCEDURES	5-1
5.3.1	Loading Procedures for the VAX-11/780	5-1
5.3.2	Loading Procedures for the VAX-11/750	5-2
5.3.3	Loading Procedures for the VAX-11/730	5-2
5.4	PROGRAM DESCRIPTION	5-6
5.4.1	Default Section	5-7
5.4.2	Silo Section	5-8
5.4.3	Modem Section	5-8
5.4.4	Configuration Section	5-8
5.5	DISTRIBUTION	5-9
5.6	MAINTENANCE HISTORY	5-10

LIST OF TABLES

Table		Page
1-1	Prompt Mode, VAX-11/780	1-3
1-2	Explicit Mode, VAX-11/780	1-4
1-3	Prompt Mode, VAX-11/750	1-5
1-4	Explicit Mode, VAX-11/750	1-5
1-5	Prompt Mode, VAX-11/730	1-7
1-6	Explicit Mode, VAX-11/730	1-7
2-1	Prompt Mode, VAX-11/780	2-3
2-2	Explicit Mode, VAX-11/780	2-4
2-3	Prompt Mode, VAX-11/750	2-5
2-4	Explicit Mode, VAX-11/750	2-5
2-5	Prompt Mode, VAX-11/730	2-7
2-6	Explicit Mode, VAX-11/730	2-7
3-1	Prompt Mode	3-3
3-2	Explicit Mode	3-4
3-3	Command File	3-4
4-1	Prompt Mode	4-3
4-2	Explicit Mode	4-3
4-3	Command File	4-4
5-1	Prompt Mode	5-3
5-2	Explicit Mode	5-4
5-3	Command File	5-5

Section 1

VAX-DISK-FORMATTER

1.1 GENERAL DESCRIPTION

This program is used to format standard Digital Equipment Corporation (DEC) RM/RP disks, emulated through the Emulex SC750, SC780, SC21/V1 or SC31 disk controllers. Up to eight units can be concurrently selected for formatting.

1.2 REQUIREMENTS

For proper program installation, the following hardware and software requirements should be observed.

1.2.1 HARDWARE REQUIREMENTS

The hardware necessary to properly run this format program consists of the following: a VAX-11 processor with 128KW memory, a console device, an Emulex SC750, SC780, SC21 or SC31 disk controller, and at least one appropriate type of supported disk drive. It is assumed the VAX CPU, memory, and Unibus Adapter are known to be functioning properly..

1.2.2 SOFTWARE REQUIREMENTS

This program runs with the diagnostic supervisor ESSAA for the VAX-11/780 processor, ECSAA for the VAX-11/750 processor, or ENSAA for the VAX-11/730 processor, Version 6.0 or later, under the VAX VMS operating system or standalone under the Diagnostic Supervisor. The appropriate DEC Diagnostic Supervisor must be installed on the system disk in the [SYSMAINT] account. For an Emulex SC21 or SC31 controller installation the Emulex-supported VMS driver (UMDRIVER) is assumed to have been installed as described in the software installation manual if the program is to be run in the On-Line mode. If this installation is for an SC750 or SC780 controller, the standard DEC VMS disk drivers are assumed to have been properly patched, if required, as described in the appropriate Emulex controller installation manual.

1.3 LOADING PROCEDURES

The complete program loading requires six procedures.

1.3.1 COPYING THE FILES ONTO THE SYSTEM DISK

The Emulex diagnostics are contained entirely on one floppy disk (Emulex part number VX9960501), or on one TU58 cassette (Emulex part number VX9960401), as appropriate to the system. To copy the program files, you must use the FLX utility program, since all VAX console media are recorded in RT11 format.

You must first log into a privileged account, then set your default directory to [SYSMAINT].

```
username: SYSTEM
password:
```

Welcome to VAX/VMS version V3.n

```
$ MCR SYSGEN
SYSGEN> CONNECT CONSOLE
SYSGEN> EXIT
$ SET DEF [SYSMAINT]
$ MCR FLX
FLX> /RS=CS1:*.730/RT
FLX> /RS=CS1:*.750/RT
FLX> /RS=CS1:*.780/RT
FLX> /RS=CS1:*.HLP/RT
FLX> /RS/IM=CS1:*.EXE/RT/IM
FLX> ^Z
$ LOG
```

NOTE

The .EXE files must be copied by using the Image mode (/IM) switch. Do not use the /IM switch when copying the .COM and .HLP files.

1.3.2 STARTING THE DIAGNOSTIC SUPERVISOR -- VAX-11/780

To begin an On-Line diagnostic session, you must first log into the system maintenance account and invoke the DEC Diagnostic Supervisor. To accomplish this procedure, enter the following underlined inputs:

```
username: FIELD
password: (service)
```

Welcome to VAX/VMS version V3.n

```
$ RUN ESSAA(cr)
```


This instruction loads the Diagnostic Supervisor into memory which then announces itself with:

```
DIAGNOSTIC SUPERVISOR. ZZ-ESSAA-6.n-xxx
DS>
```

1.3.2.1 Starting the Diagnostic Supervisor (Off-Line)

To begin an Off-Line diagnostic session, you must first bootstrap the DEC Diagnostic Supervisor. To accomplish this procedure, remove the floppy disk labeled "Local Console" from the drive, and insert the Diagnostic Supervisor floppy disk, then enter the following instruction:

```
>>>^P
>>>HALT
>>>BOOT
```

This instruction loads the Diagnostic Supervisor into memory which then announces itself with:

```
DIAGNOSTIC SUPERVISOR. ZZ-ESSAA-6.n-xxx
DS>
```

1.3.3 OPERATING PROCEDURES FOR THE VAX-11/780

The desired disk device must now be attached and selected. There are two ways in which this procedure can be done: by using the Prompt mode, or by using the Explicit (No Prompt) mode. Examples for each procedure are listed in Tables 1-1 and 1-2. The underlined text indicates information which needs to be typed into the console by the user. It should follow the Diagnostic Supervisor Prompt symbol which is "DS>" or "?".

Table 1-1. Prompt Mode, VAX-11/780

SC780	SC21/SC31
DS> <u>LOAD EDSKF</u>	DS> <u>LOAD EDSKF</u>
DS> <u>ATTACH</u>	DS> <u>ATTACH</u>
DEVICE TYPE ? <u>RH780</u>	DEVICE TYPE ? <u>DW780</u>
DEVICE LINK ? <u>SBI</u>	DEVICE LINK ? <u>SBI</u>
DEVICE NAME ? <u>RH0</u>	DEVICE NAME ? <u>DW0</u>
TR ? <u>11</u>	TR ? <u>3</u>
BR ? <u>5</u>	BR ? <u>4</u>
DS> <u>ATTACH</u>	DS> <u>ATTACH</u>
DEVICE TYPE ? <u>RM</u>	DEVICE TYPE ? <u>SC21*</u>
DEVICE LINK ? <u>RH0</u>	DEVICE LINK ? <u>DW0</u>
DEVICE NAME ? <u>DRA0</u>	DEVICE NAME ? <u>UMA0</u>
DS> <u>SELECT DRA0</u>	CSR ? <u>776700</u>
	VECTOR ? <u>254</u>
	DS> <u>SELECT UMA0</u>

*or SC31

Table 1-2. Explicit Mode, VAX-11/780

SC780	SC21/SC31
DS> <u>LOAD EDSKF</u>	DS> <u>LOAD EDSKF</u>
DS> <u>ATT RH780 SBI RH0 5 11</u>	DS> <u>ATT DW780 SBI DW0 3 4</u>
DS> <u>ATT RM RH0 DRA0</u>	DS> <u>ATT SC21* DW0 UMA0 776700 254</u>
DS> <u>SEL DRA0</u>	DS> <u>SEL UMA0</u>

*or SC31

Once the Unit Under Test (UUT) has been ATTached and SElected, the diagnostic program must be started as follows:

DS> STart[/ (switches)]

See the VAX Diagnostic User's Guide, DEC part number EK-VX11D-UG for the description of the available switches.

1.3.4 STARTING THE DIAGNOSTIC SUPERVISOR -- VAX-11/750

To begin an On-Line diagnostic session, you must first log into the system maintenance account and invoke the DEC Diagnostic Supervisor. To accomplish this procedure, enter the following underlined inputs:

username: FIELD
password: (service)

Welcome to VAX/VMS version V3.n

\$ RUN ECSAA(cr)

This instruction loads the Diagnostic Supervisor into memory which then announces itself with:

DIAGNOSTIC SUPERVISOR. ZZ-ECSAA-6.n-xxx
DS>

1.3.4.1 Starting the Diagnostic Supervisor (Off-Line)

To begin an Off-Line diagnostic session, you must first bootstrap the DEC Diagnostic Supervisor. To accomplish this procedure, remove the TU58 cassette labeled "Local Console" from the drive, insert the Diagnostic Supervisor cassette, place the bootstrap device select switch in the TU58 position (usually position "A"), and press the RESET button. This procedure loads the Diagnostic Supervisor into memory which then announces itself with:

DIAGNOSTIC SUPERVISOR. ZZ-ECSAA-6.n-xxx
DS>

1.3.5 OPERATING PROCEDURES FOR THE VAX-11/750

The desired disk device must now be attached and selected. There are two ways in which this procedure can be done: by using the Prompt mode, or by using the Explicit (No Prompt) mode. Examples for each procedure are listed in Tables 1-3 and 1-4. The underlined text indicates information which needs to be typed into the console by the user. It should follow the Diagnostic Supervisor Prompt symbol which is "DS>" or "?".

Table 1-3. Prompt Mode, VAX-11/750

SC750	SC21/SC31
DS> <u>LOAD EDSKF</u> DS> <u>ATTACH</u> DEVICE TYPE ? <u>RH750</u> DEVICE LINK ? <u>CMI</u> DEVICE NAME ? <u>RH0</u> DS> <u>ATTACH</u> DEVICE TYPE ? <u>RM</u> DEVICE LINK ? <u>RH0</u> DEVICE NAME ? <u>DRA0</u> DS> <u>SELECT DRA0</u>	DS> <u>LOAD EDSKF</u> DS> <u>ATTACH</u> DEVICE TYPE ? <u>DW750</u> DEVICE LINK ? <u>CMI</u> DEVICE NAME ? <u>DW0</u> DS> <u>ATTACH</u> DEVICE TYPE ? <u>SC21*</u> DEVICE LINK ? <u>DW0</u> DEVICE NAME ? <u>UMA0</u> CSR ? <u>776700</u> VECTOR ? <u>254</u> DS> <u>SELECT UMA0</u>

*or SC31

Table 1-4. Explicit Mode, VAX-11/750

SC750	SC21/SC31
DS> <u>LOAD EDSKF</u> DS> <u>ATT RH750 SBI RH0</u> DS> <u>ATT RM RH0 DRA0</u> DS> <u>SEL DRA0</u>	DS> <u>LOAD EDSKF</u> DS> <u>ATT DW750 SBI DW0</u> DS> <u>ATT SC21* DW0 UMA0 776700 254</u> DS> <u>SEL UMA0</u>

*or SC31

Once the UUT has been ATTached and SElected, the diagnostic program must be started as follows:

DS> SStart[/ (switches)]

See the VAX Diagnostic User's Guide, DEC part number EK-VX11D-UG for the description of the available switches.

1.3.6 STARTING THE DIAGNOSTIC SUPERVISOR -- VAX-11/730

To begin an On-Line diagnostic session, you must first log into the system maintenance account and invoke the DEC Diagnostic Supervisor. To accomplish this procedure, enter the following underlined inputs:

```
username: FIELD
password: (service)
```

Welcome to VAX/VMS version V3.n

```
$ RUN ENSAA(cr)
```

This instruction loads the Diagnostic Supervisor into memory which then announces itself with:

```
DIAGNOSTIC SUPERVISOR. ZZ-ENSAA-6.n-xxx
DS>
```

1.3.6.1 Starting the Diagnostic Supervisor (Off-Line)

To begin an Off-Line diagnostic session, you must first bootstrap the DEC Diagnostic Supervisor. To accomplish this procedure, remove the TU58 cassette labeled "Local Console" from the Internal drive (unit 1) and insert the "Load Path" diagnostic cassette (#37), then insert the Emulex diagnostic cassette in the External drive (unit 0), and enter the following underlined inputs:

```
>>>I
>>>L/P/S:FE00 DD1:ENSAA.EXE
>>>S 10000
```

This instruction loads the Diagnostic Supervisor into memory which then announces itself with:

```
DIAGNOSTIC SUPERVISOR. ZZ-ENSAA-6.n-xxx
DS>
```

1.3.7 OPERATING PROCEDURES FOR THE VAX-11/730

The desired disk device must now be attached and selected. There are two ways in which this procedure can be done: by using the Prompt mode, or by using the Explicit (No Prompt) mode. Examples for each procedure are listed in Tables 1-5 and 1-6. The underlined text indicates information which needs to be typed into the console by the user. It should follow the Diagnostic Supervisor Prompt symbol which is "DS>" or "?".

Table 1-5. Prompt Mode, VAX-11/730

SC21/SC31

```

DS> LOAD EDSKF
DS> ATTACH
DEVICE TYPE ? DW730
DEVICE LINK ? HUB
DEVICE NAME ? DW0
DS> ATTACH
DEVICE TYPE ? SC21*
DEVICE LINK ? DW0
DEVICE NAME ? UMA0
CSR ? 776700
VECTOR ? 254
DS> SELECT UMA0

```

*or SC31

Table 1-6. Explicit Mode, VAX-11/730

SC21/SC31

```

DS> LOAD EDSKF
DS> ATT DW730 HUB DW0
DS> ATT SC21* DW0 UMA0 776700 254
DS> SEL UMA0

```

*or SC31

Once the UUT has been ATTached and SElected, the diagnostic program must be started as follows:

DS> STart[/((switches))]

See the VAX Diagnostic User's Guide, DEC part number EK-VX11D-UG for the description of the available switches.

1.4 PROGRAM DESCRIPTION

The formatter may be used to select one of eight functions (sections) which are described below. Some functions are common to most sections; with the exception of HELP, INITSF, and REBUILD, all sections begin by reading the bad sector file (or the skip sector file if applicable), verifying the format of the file, and displaying the contents of the file. If the file is either unreadable or corrupted, the section is aborted. The operator should then use section INITSF to restore the file to a known, valid state.

Any section which Writes to the disk, checks to ensure that the mounted volume is labeled "SCRATCH". If not, a warning message is printed and the operator is requested to indicate whether the program is or is not to continue.

Since this formatter supports both disks which employ skip sectoring (RM80) and those which do not (RM02/03/05, and RP05/06), descriptions below and messages printed by the diagnostic itself may make parenthetical references to the skip sector file. These references should be ignored, if not applicable.

1.4.1 HELP SECTION

This section prints a description of the operation of the formatter, including:

- Types of disks supported,
- List and description of the sections,
- List and description of the event flags which are applicable to formatter operation.

1.4.2 FORVER SECTION

This section has two functions: initialize bad sectors and to format a new or corrupt disk pack.

First, this section initializes the bad sector file (or the skip sector file if applicable for the selected disk) to no entries. Before initializing the bad (or skip) sector file, a warning message is displayed and the operator is asked to either continue or abort. This section requires the operator to enter the desired volume serial number (which is stored in the bad or skip sector file).

Second, this section formats a new or corrupted pack. The pack is formatted one track at a time. A surface analysis is performed at the completion of the format, and any bad sector discovered is flagged and added to the bad (or skip) sector file. The homeblock is written with the name "SCRATCH". The user should be aware that the bad (or skip) sector file is not updated until the surface verification is fully completed.

1.4.3 VERIFY SECTION

This section is used to perform a surface analysis of the selected disk. Any bad sectors found are flagged and added to the bad (or skip) sector file. The homeblock is written with the name "SCRATCH". The user should be aware that the bad (or skip) sector file is not updated until surface verification is fully completed.

1.4.4 READALL SECTION

This section is used to Read every sector on the pack and to print a report of any errors found. This section does not Write to the disk and may therefore be used with a non-scratch pack that contains no warning. The error report produced indicates whether the error found was or was not previously flagged.

1.4.5 UPDATE SECTION

This section is used to manually add entries to the bad (or skip) sector file. The operator indicates whether the entries to be added are logical block numbers or physical specifications (cylinder, track, sector). This section should not be used unless the user has a complete understanding of the use and structure of the bad (or skip) sector file).

1.4.6 REBUILD SECTION

This section is a combination of FORVER and UPDATE. The bad (or skip) sector file is initialized, after which the operator may manually enter the desired entries in the file.

1.4.7 DISPLAY SECTION

This section is used to display the contents of the bad (or skip) sector file. This program section performs Read-only operations which may be used with a non-scratch disk that contains no warning.

1.5 PROGRAM OPTIONS

Program options use the following Event Flags:

Quick:	If set, reduces the number of track Read operations from five to one during verification.
Event Flag 23:	If set, causes the logical block number to be printed after each track accessed
Event Flag 22:	If set, causes the logical block number to be printed after every 100 cylinders accessed
Event Flag 21:	If set, causes shortened error messages (only device register contents, not bus adapter register contents)
Event Flag 20:	If set, forces single-track access in Stand-Alone mode

Event Flag 19: If set, causes only the FE cylinders to be formatted

Event Flag 18: If set, causes bypass of the surface verification

1.6 DISTRIBUTION

The SC750/SC780, SC21/SC31 Disk Formatter Program is contained entirely on one floppy disk (Emulex part number VX9960501), or on one TU58 cassette (Emulex part number VX9960401), as appropriate to the system. The contents of this unit which apply to the SC750/SC780 and SC21/SC31 are defined as follows:

EDSKF.EXE	The SC750/SC780, SC21/SC31 disk formatter program executable image.
-----------	---

The listings for the Emulex SC750/780, SC21/SC31 Disk Formatter Program are identified as Emulex part number VX9960061. These listings contain the assembly list file (EDSKF.LIS) and the MAP file (EDSKF.MAP) of the SC750/SC780, SC21/SC31 Disk Formatter Program.

NOTE

These listing files are proprietary information that belong to Emulex. They are released only with appropriate Software Source license.

2.1 GENERAL DESCRIPTION

This program is designed to exercise standard Digital Equipment Corporation (DEC) RM/RP/RK disks and additional expanded disk configurations supported by the Emulex SC750, SC780, SC12/V, SC21/V1 and SC31 disk controllers.

2.2 REQUIREMENTS

For proper program installation, the following hardware and software requirements should be observed.

2.2.1 HARDWARE REQUIREMENTS

The hardware necessary to properly run this diagnostic test consists of the following components: a VAX-11 processor with 128KW memory, a console device, an Emulex SC750, SC780 SC12, SC21, or SC31 disk controller and at least one appropriate type of supported disk drive. It is assumed that the VAX CPU, memory, and Unibus Adapter are known to be functioning properly.

2.2.2 SOFTWARE REQUIREMENTS

This program runs with the diagnostic supervisor ESSAA for the VAX-11/780 processor, ECSAA for the VAX-11/750 processor, or ENSAA for the VAX-11/730 processor, Version 6.0 or later, under the VAX VMS operating system or standalone under the Diagnostic supervisor. The appropriate DEC Diagnostic Supervisor must be installed on the system disk in the [SYSMAINT] account. For an Emulex SC21 or SC31 controller installation, the Emulex-supported VMS driver (UMDRIVER) is assumed to have been installed as described in the software installation manual. If this installation is for an SC750 or SC780 controller, the standard DEC VMS disk drivers are assumed to have been properly patched, if required, as described in the appropriate installation manual.

2.3 LOADING PROCEDURES

The complete program loading requires seven procedures.

2.3.1 COPYING THE FILES ONTO THE SYSTEM DISK

The Emulex diagnostics are contained entirely on one floppy disk (Emulex part number VX9960501), or on one TU58 cassette (Emulex part number VX9960401), as appropriate to the system. To copy the program files you must use the FLX utility program since all VAX console media are recorded in RT11 format.

You must first log into a privileged account, then set your default directory to [SYSMAINT].

```
username: SYSTEM
password:
```

Welcome to VAX/VMS version V3.n

```
$ MCR SYSGEN
SYSGEN> CONNECT CONSOLE
SYSGEN> EXIT
$ SET DEF [SYSMAINT]
$ MCR FLX
FLX> /RS=CS1:*.730/RT
FLX> /RS=CS1:*.750/RT
FLX> /RS=CS1:*.780/RT
FLX> /RS=CS1:*.HLP/RT
FLX> /RS/IM=CS1:*.EXE/RT/IM
FLX> ^Z
$ LOG
```

NOTE

The .EXE files must be copied by using the Image mode (/IM) switch. Do not use the /IM switch when copying the .COM and .HLP files.

2.3.2 STARTING THE DIAGNOSTIC SUPERVISOR -- VAX-11/780

To begin an On-Line diagnostic session, you must first log into the system maintenance account and invoke the DEC Diagnostic Supervisor. To accomplish this procedure, enter the following underlined inputs:

```
username: FIELD
password: (service)
```

Welcome to VAX/VMS version V3.n

```
$ RUN ESSAA(cr)
```

This instruction loads the Diagnostic Supervisor into memory which then announces itself with:

```
DIAGNOSTIC SUPERVISOR. ZZ-ESSAA-6.n-xxx
DS>
```

2.3.2.1 Starting the Diagnostic Supervisor (Off-Line)

To begin an Off-Line diagnostic session, you must first bootstrap the DEC Diagnostic Supervisor. To accomplish this procedure, remove the floppy disk labeled "Local Console" from the drive, insert the Diagnostic Supervisor floppy disk, then enter the following instruction:

```
>>>^P(cr)
>>>HALT(cr)
>>>BOOT(cr)
```

This instruction loads the Diagnostic Supervisor into memory which then announces itself with:

```
DIAGNOSTIC SUPERVISOR. ZZ-ESSAA-6.n-xxx
DS>
```

2.3.3 OPERATING PROCEDURES FOR THE VAX-11/780

The desired disk device must now be attached and selected. There are two ways in which this procedure can be done: by using the Prompt mode, or by using the Explicit (No Prompt) mode. Examples for each procedure are listed in Tables 2-1, and 2-2. The underlined text indicates information which needs to be typed into the console by the user. It should follow the Diagnostic Supervisor Prompt symbol which is "DS>" or "?".

Table 2-1. Prompt Mode, VAX-11/780

SC780
SC21/SC31

```
DS> LOAD EDSKR
DS> ATTACH
DEVICE TYPE ? RH780
DEVICE LINK ? SBI
DEVICE NAME ? RH0
TR ? 11
BR ? 5
DS> ATTACH
DEVICE TYPE ? RM
DEVICE LINK ? RH0
DEVICE NAME ? DRA0
DS> SELECT DRA0
```

```
DS> LOAD EDSKR
DS> ATTACH
DEVICE TYPE ? DW780
DEVICE LINK ? SBI
DEVICE NAME ? DW0
TR ? 3
BR ? 4
DS> ATTACH
DEVICE TYPE ? SC21
DEVICE LINK ? DW0
DEVICE NAME ? UMA
CSR ? 776700
VECTOR ? 254
BR ? 5
DS> SELECT UMA
```

Table 2-2. Explicit Mode, VAX-11/780

SC780	SC21/SC31
DS> <u>LOAD EDSKR</u>	DS> <u>LOAD EDSKR</u>
DS> <u>ATT RH780 SBI RH0 5 11</u>	DS> <u>ATT DW780 SBI DW0 3 4</u>
DS> <u>ATT RM RH0 DRA0</u>	DS> <u>ATT SC21 DW0 UMA 776700 254 5</u>
DS> <u>SEL DRA0</u>	DS> <u>SEL UMA</u>

Once the Unit Under Test (UUT) has been ATTached and SElected, the diagnostic program must be started as follows:

DS> STart[/((switches))]

See the VAX Diagnostic User's Guide, DEC part number EK-VX11D-UG for the description of the available switches.

2.3.4 STARTING THE DIAGNOSTIC SUPERVISOR -- VAX-11/750

To begin an On-Line diagnostic session, you must first log into the system maintenance account and invoke the DEC Diagnostic Supervisor. To accomplish this procedure, enter the following underlined inputs:

username: FIELD
password: (service)

Welcome to VAX/VMS version V3.n

\$ RUN ECSAA(cr)

This instruction loads the Diagnostic Supervisor into memory which then announces itself with:

DIAGNOSTIC SUPERVISOR. ZZ-ECSAA-6.n-xxx
DS>

2.3.4.1 Starting the Diagnostic Supervisor (Off-Line)

To begin an Off-Line diagnostic session, you must first bootstrap the DEC Diagnostic Supervisor. To accomplish this procedure, remove the TU58 cassette labeled "Local Console" from the drive, insert the Diagnostic Supervisor cassette, place the bootstrap device select switch in the TU58 position (usually switch position "A"), and press the RESET button. This procedure loads the Diagnostic Supervisor into memory which then announces itself with:

DIAGNOSTIC SUPERVISOR. ZZ-ECSAA-6.n-xxx
DS>

2.3.5 OPERATING PROCEDURES FOR THE VAX-11/750

The desired disk device must now be attached and selected. There are two ways in which this procedure can be done: by using the Prompt mode, or by using the Explicit (No Prompt) mode. Examples for each procedure are listed in Tables 2-3, and 2-4. The underlined text indicates information which needs to be typed into the console by the user. It should follow the Diagnostic Supervisor Prompt symbol which is "DS>" or "?".

Table 2-3. Prompt Mode, VAX-11/750

SC750	SC21/SC31
DS> <u>LOAD EDSKR</u> DS> <u>ATTACH</u> DEVICE TYPE ? <u>RH750</u> DEVICE LINK ? <u>CMI</u> DEVICE NAME ? <u>RH0</u> DS> <u>ATTACH</u> DEVICE TYPE ? <u>RM</u> DEVICE LINK ? <u>RH0</u> DEVICE NAME ? <u>DRA0</u> DS> <u>SELECT DRA0</u>	DS> <u>LOAD EDSKR</u> DS> <u>ATTACH</u> DEVICE TYPE ? <u>DW750</u> DEVICE LINK ? <u>CMI</u> DEVICE NAME ? <u>DW0</u> DS> <u>ATTACH</u> DEVICE TYPE ? <u>SC21</u> DEVICE LINK ? <u>DW0</u> DEVICE NAME ? <u>UMA</u> CSR ? <u>776700</u> VECTOR ? <u>254</u> BR ? <u>5</u> DS> <u>SELECT UMA</u>

Table 2-4. Explicit Mode, VAX-11/750

SC750	SC21/SC31
DS> <u>LOAD EDSKR</u> DS> <u>ATT RH750 SBI RH0</u> DS> <u>ATT RM RH0 DRA0</u> DS> <u>SEL DRA0</u>	DS> <u>LOAD EDSKR</u> DS> <u>ATT DW750 SBI DW0</u> DS> <u>ATT SC21 DW0 UMA 776700 254 5</u> DS> <u>SEL UMA</u>

Once the UUT has been ATTached and SElected, the diagnostic program must be started as follows:

DS> STart[/ (switches)]

See the VAX Diagnostic User's Guide, DEC part number EK-VX11D-UG for the description of the available switches.

2.3.6 STARTING THE DIAGNOSTIC SUPERVISOR -- VAX-11/730

To begin an On-Line diagnostic session, you must first log into the system maintenance account and invoke the DEC Diagnostic Supervisor. To accomplish this procedure, enter the following underlined inputs:

```
username: FIELD  
password: (service)
```

```
Welcome to VAX/VMS version V3.n
```

```
$ RUN ENSAA(cr)
```

This instruction loads the Diagnostic Supervisor into memory, which then announces itself with:

```
DIAGNOSTIC SUPERVISOR. ZZ-ENSAA-6.n-xxx  
DS>
```

2.3.6.1 Starting the Diagnostic Supervisor (Off-Line)

To begin an Off-Line diagnostic session, you must first bootstrap the DEC Diagnostic Supervisor. To accomplish this procedure, remove the TU58 cassette labeled "Local Console" from the internal drive (unit 1), and insert the "Load Path" diagnostic cassette (#37). Then insert the Emulex diagnostic cassette in the External drive (unit 0), and enter the following underlined inputs:

```
>>>I(cr)  
>>>L/P/S:FE00 DDL:ENSAA.EXE(cr)  
>>>S 10000(cr)
```

This instruction loads the Diagnostic Supervisor into memory which then announces itself with:

```
DIAGNOSTIC SUPERVISOR. ZZ-ENSAA-6.n-xxx  
DS>
```

2.3.7 OPERATING PROCEDURES FOR THE VAX-11/730

The SC12, SC21 or SC31 device must now be ATTached and SElected. There are two ways in which this procedure can be done: by using the Prompt mode, or by using the Explicit (No Prompt) mode. Examples for each procedure are listed in Tables 2-5 and 2-6. The underlined text indicates information which needs to be typed into the console by the user. It should follow the Diagnostic Supervisor Prompt symbol which is " DS>" or "?".

Table 2-5. Prompt Mode, VAX-11/730

SC12	SC21/SC31
<pre> DS> <u>LOAD EDSKR</u> DS> <u>ATTACH</u> DEVICE TYPE ? <u>DW730</u> DEVICE LINK ? <u>HUB</u> DEVICE NAME ? <u>DW0</u> DS> <u>ATTACH</u> DEVICE TYPE ? <u>RK611</u> DEVICE LINK ? <u>DW0</u> DEVICE NAME ? <u>DRA0</u> DEVICE NAME ? <u>DMA</u> CSR ? <u>777440</u> VEC ? <u>210</u> BR ? <u>5</u> DS> <u>ATTACH</u> DEVICE TYPE ? <u>RK</u> DEVICE LINK ? <u>DMA</u> DEVICE NAME ? <u>DMA0</u> DS> <u>SELECT DMA0</u> </pre>	<pre> DS> <u>LOAD EDSKR</u> DS> <u>ATTACH</u> DEVICE TYPE ? <u>DW730</u> DEVICE LINK ? <u>HUB</u> DEVICE NAME ? <u>DW0</u> DS> <u>ATTACH</u> DEVICE TYPE ? <u>SC21</u> DEVICE LINK ? <u>DW0</u> DEVICE NAME ? <u>UMA</u> CSR ? <u>776700</u> VECTOR ? <u>254</u> BR ? <u>5</u> DS> <u>SELECT UMA</u> </pre>

Table 2-6. Explicit Mode, VAX-11/730

SC12	SC21/SC31
<pre> DS> <u>LOAD EDSKR</u> DS> <u>ATT DW730 HUB DW0</u> DS> <u>ATT RK611 DW0 DMA 777440 210 5</u> DS> <u>ATT RK DMA DMA0</u> </pre>	<pre> DS> <u>LOAD EDSKR</u> DS> <u>ATT DW730 HUB DW0</u> DS> <u>ATT UM DW0 UMA 776700 254 5</u> DS> <u>SEL UMA</u> DS> <u>SELECT DMA0</u> </pre>

Once the UUT has been ATTached and SElected, the diagnostic program must be started as follows:

```
DS> STart[/ (switches)]
```

See the VAX Diagnostic User's Guide, DEC part number EK-VX11D-UG for the description of the available switches.

2.4 PROGRAM DESCRIPTION

This program contains four tests which exercise the SC750, SC780, SC12, SC21/V1 and SC31 disk controllers. These tests are further

grouped into five sections: Default, Media, Multi-Drive, Qualification, and Seek Timing. These section names must be specified with the Start command to invoke each test.

2.4.1 DEFAULT SECTION

This section issues each of the drive function instructions to ensure the drive(s) can support all the drive commands. After all the non-data transfer functions have been tested, the test issues a Write, Write Check and Read sequence command set to each of a group of disk addresses.

The next test performs Seek operations between cylinder 000 and cylinders: 001, 002, 004, 008, 016, 032, 064, 128, 256, and 512. Each Seek range is timed, and an average time is calculated and displayed on the console.

This section is run by default if no section name is specified in the Start command. The default section consists of the following tests:

Test 1: Qualification
Test 2: Seek Timing

2.4.2 QUALIFICATION SECTION

This section issues each of the drive function instructions to ensure the drive(s) can support all the drive commands. After all the non-data transfer functions have been tested, the test issues a Write, Write Check, and Read sequence command set to each of a group of disk addresses. This section is run by default if no section name is specified in the Start command. The qualification section consists of the following test:

Test 1: Qualification

2.4.3 SEEK TIMING SECTION

This test performs Seek operations between cylinder 000 and cylinders: 001, 002, 004, 008, 016, 032, 064, 128, 256, and 512. Each Seek range is timed and an average time is calculated and displayed on the console. This section is run by default if no section name is specified in the Start command. The Seek Timing section consists of the following test:

Test 2: Seek Timing

2.4.4 MEDIA SECTION

This section Writes and Write Checks every sector on the disk by using an entire track for each operation. Five different patterns are written onto each sector, to attempt verification of the usability of a given sector. This section is not run by default and must be explicitly requested as follows:

DS> STart/SECTion:MEdia

The media section consists of the following test:

Test 3: Media Surface Verification

2.4.5 MULTI-DRIVE SECTION

This test tests up to eight drives concurrently by transferring random disk addresses. If fixed media disks are selected (RM80 or RP07), the operator is asked the following questions:

Fixed media devices (RM80 or RP07) are selected.
This test will destroy customer data if run on
the entire surface. If you do not want to destroy
the data, only FE cylinders will be used.
Do you want to use the entire pack ? [(NO), YES]

If the operator responds "NO", then only the FE cylinders are to be used on RM80 or RP07 type disks. If the response is "YES", then the operator is further asked:

Are you sure ? [(NO), YES]

If the response is "NO", the test is aborted. If the response is "YES" the test proceeds. This section does not run by default and must be explicitly requested as follows:

DS> STart/SECTion:Multi

The Multi-Drive section consists of the following test:

Test 4: Multi-Drive Functional Test

2.5 DISTRIBUTION

The Emulex disk reliability test is contained entirely on one floppy disk (Emulex part number VX9960501), or on one TU58 cassette (Emulex part number VX9960401), as appropriate to the system. The contents of this unit which apply to the SC750, SC780, SC12, SC21 or SC31 are defined as follows:

EDSKR.EXE The SC750, SC780, SC12, SC21 and SC31 disk
 reliability program executable image.

The listings for the Emulex disk reliability program are identified as Emulex part number VX9960062. These listings contain the assembly list file (EDSKR.LIS) and the MAP file (EDSKR.MAP) of the disk reliability program.

NOTE

These listing files are proprietary information that belong to Emulex. They are released only with appropriate Software Source license.

3.1 GENERAL DESCRIPTION

This diagnostic test program is designed to aid in the acceptance testing, installation checkout, and corrective maintenance of the Emulex SC21/V1 and SC31 disk controllers.

3.2 REQUIREMENTS

For proper program installation, the following hardware and software requirements should be observed.

3.2.1 HARDWARE REQUIREMENTS

The hardware necessary to properly run this diagnostic test consists of the following components: a VAX-11 processor with 128KW memory, a unibus adapter, a console device, an Emulex SC21 or SC31 disk controller and at least one supported disk drive. It is assumed that the VAX CPU, memory, and Unibus Adapter are known to be functioning properly.

3.2.2 SOFTWARE REQUIREMENTS

This program runs with the diagnostic supervisor ESSAA for the VAX-11/780 processor, ECSAA for the VAX-11/750 processor, or ENSAA for the VAX-11/730 processor, Version 6.0 or later.

3.3 LOADING PROCEDURES

The complete program loading requires three procedures.

3.3.1 LOADING PROCEDURES FOR THE VAX-11/780

To begin an Off-Line diagnostic session, you must first bootstrap the Digital Equipment Corporation (DEC) Diagnostic Supervisor. To accomplish this bootstrap, remove the floppy disk labeled "Local Console" from the drive and insert the DEC-supplied DW780 channel diagnostic floppy disk, then enter the following instruction:

```
>>>^P
>>>HALT
>>>BOOT
```

This instruction loads the Diagnostic Supervisor into memory which then announces itself with:

DIAGNOSTIC SUPERVISOR. ZZ-ESSAA-6.n-xxx
DS>

Remove the DEC DW780 channel diagnostic floppy disk and place the Emulex-supplied diagnostic floppy disk (Emulex part number VX9960501) in the drive. The diagnostic program must now be loaded and the SC21 or SC31 device must be ATTached and SElected. There are three ways in which this procedure can be done: by using the Prompt mode, by using the Explicit (No Prompt) mode, or by using the Command File. Examples of each procedure are listed in Tables 3-1, 3-2, and 3-3. The underlined text indicates information which needs to be typed into the console by the user. It should follow the appropriate system prompt symbol which is a "DS>" or "?".

3.3.2 LOADING PROCEDURES FOR THE VAX-11/750

To begin an offline diagnostic session, you must first bootstrap the DEC Diagnostic Supervisor. To accomplish this procedure, remove the TU58 cassette labeled "Local Console" from the drive, insert the DEC-supplied RH750/DW750 channel diagnostic cassette, place the boot device select switch in the TU58 position, and press the RESET button. This procedure loads the Diagnostic Supervisor into memory which then announces itself with:

DIAGNOSTIC SUPERVISOR. ZZ-ECSAA-6.n-xxx
DS>

Remove the DEC RH75-/DW750 diagnostic cassette and place the Emulex-supplied diagnostic cassette (Emulex part number VX9960401) in the drive. The diagnostic program must now be loaded and the SC21 or SC31 device must be ATTached and SElected. There are three ways in which this procedure can be done: by using the Prompt mode, by using the Explicit (No Prompt) mode, or by using the Command File. Examples of each procedure are listed in Tables 3-1, 3-2, and 3-3. The underlined text indicates information which needs to be typed into the console by the user. It should follow the appropriate system prompt symbol which is a "DS>" or "?".

3.3.3 LOADING PROCEDURES FOR THE VAX-11/730

To begin an Off-Line diagnostic session, you must first bootstrap the DEC Diagnostic Supervisor. To accomplish this procedure, remove the TU58 cassette labeled "Local Console" from the Internal drive (unit 1), and insert the DEC-supplied "Load Path" diagnostic cassette (#37). Insert the Emulex-supplied diagnostic cassette (Emulex part number VX9960401) in the External drive (unit 0), and enter the following instruction:

```
>>>I  
>>>L/P/S:FE00 DD1:ENSAA.EXE  
>>>S 10000
```

This instruction loads the Diagnostic Supervisor into memory which then announces itself with:

```
DIAGNOSTIC SUPERVISOR. ZZ-ENSAA-6.n-xxx
DS>
```

The diagnostic program must now be loaded and the SC21 or SC31 device must be ATTached and SElected. There are three ways in which this procedure can be done: by using the Prompt mode, by using the Explicit (No Prompt) mode, or by using the Command File. Examples of each are shown in tables 3-1, 3-2, and 3-3. The underlined text indicates information which needs to be typed into the console by the user. It should follow the appropriate system prompt symbol which is a "DS>" or "?".

Table 3-1. Prompt Mode

VAX-11/780	VAX-11/750	VAX-11/730
DS> <u>LOAD ESC21</u> DS> <u>ATTACH</u> DEVICE TYPE ? <u>DW780</u> DEVICE LINK ? <u>SBI</u> DEVICE NAME ? <u>DW0</u> TR ? <u>3</u> BR ? <u>4</u> DS> <u>ATTACH</u> DEVICE TYPE ? <u>SC21</u> DEVICE LINK ? <u>DW0</u> DEVICE NAME ? <u>UMA</u> CSR ? <u>776700</u> DS> <u>SELECT UMA</u>	DS> <u>LOAD ECS21</u> DS> <u>ATTACH</u> DEVICE TYPE ? <u>DW750</u> DEVICE LINK ? <u>CMI</u> DEVICE NAME ? <u>DW0</u> DS> <u>ATTACH</u> DEVICE TYPE ? <u>SC21</u> DEVICE LINK ? <u>DW0</u> DEVICE NAME ? <u>UMA</u> CSR ? <u>776700</u> DS> <u>SELECT UMA</u>	DS> <u>LOAD ESC21</u> DS> <u>ATTATCH</u> DEVICE TYPE ? <u>DW730</u> DEVICE LINK ? <u>HUB</u> DEVICE NAME ? <u>DW0</u> DS> <u>ATTACH</u> DEVICE TYPE ? <u>SC21</u> DEVICE LINK ? <u>DW0</u> DEVICE NAME ? <u>UMA</u> CSR ? <u>776700</u> DS> <u>SELECT UMA</u>

Table 3-2. Explicit Mode

VAX-11/780	VAX-11/750
DS> <u>LOAD ESC21</u>	DS> <u>LOAD ESC21</u>
DS> <u>ATT DW780 SBI DW0 3 4</u>	DS> <u>ATT DW750 CMI DW0</u>
DS> <u>ATT SC21 DW0 UMA 776700</u>	DS> <u>ATT SC21 DW0 UMA 776700</u>
DS> <u>SELECT UMA</u>	DS> <u>SELECT UMA</u>
VAX-11/730	
DS> <u>LOAD ESC21</u>	
DS> <u>ATT DW730 HUB DW0</u>	
DS> <u>ATT SC21 DW0 UMA 776700</u>	
DS> <u>SELECT UMA</u>	

Table 3-3. Command File

VAX-11/780	VAX-11/750
DS> <u>@ESC21.780</u>	DS> <u>@ESC21.750</u>
DS> <u>LOAD ESC21</u>	DS> <u>LOAD ESC21</u>
DS> <u>ATT DW780 SBI DW0 3 4</u>	DS> <u>ATT DW750 CMI DW0</u>
DS> <u>ATT SC21 DW0 UMA 776700</u>	DS> <u>ATT SC21 DW0 UMA 776700</u>
DS> <u>SELECT UMA</u>	DS> <u>SELECT UMA</u>
DS> <u>SET TRACE</u>	DS> <u>SET TRACE</u>
VAX-11/730	
DS> <u>@ESC21.730</u>	
DS> <u>LOAD ESC21</u>	
DS> <u>ATT DW730 HUB DW0</u>	
DS> <u>ATT SC21 DW0 UMA 776700</u>	
DS> <u>SELECT UMA</u>	

Once the Unit Under Test (UUT) has been SELECTed, the diagnostic program must be started as follows:

DS> STart[/ (switches)]

See the VAX Diagnostic User's Guide, DEC part number EK-VX11D-UG, for the description of the available switches.

3.4 PROGRAM DESCRIPTION

This program contains 21 tests which check the SC21/V1 or SC31 disk controller. These tests are further divided into two sections: Default and Configuration. When the program is first started it responds with:

```
..program: Emulex SC21/SC31 Disk Controller Diagnostic, Rev n
Testing:  _UMA
```

3.4.1 DEFAULT SECTION

This section checks the basic SC21/V1 or SC31 controller functions such as register read/write, correct error detection, controller initialization, maintenance mode features, disk addressability, and bus address checks. This section is run by default if no section name is specified in the Start command. The Default Section consists of the following tests:

```
Test 1:  Address all registers
Test 2:  CS1 register (all 1 & 0)
Test 3:  Function bits (moving 1 & 0)
Test 4:  WC register (all 1 & 0)
Test 5:  WC register (moving 1 & 0)
Test 6:  BA register (all 1 & 0)
Test 7:  BA register (moving 1 & 0)
Test 8:  MR1 bits can be set and cleared
Test 9:  DC register (all 1 & 0)
Test 10: DC register (moving 1 & 0)
Test 11: DA register (all 1 & 0)
Test 12: DA register (moving 1 & 0)
Test 13: Invalid commands give error
Test 14: Invalid DB access gives error
Test 15: SC bit set causes i
Test 16: IE & RDY set cause interrupt
Test 17: Check that pack ack sets VV
Test 18: Test IVC bit
Test 19: Increment bus address register
Test 20: Test BAI bit
```

3.4.2 CONFIGURATION SECTION

This section accesses the SC21 or SC31 DT, SN, and HR registers to obtain the controller configuration. The information obtained is output in the following format:

Emulex SC21/SC31 Disk Controller CSR [177777]
vector [377] is configured as an [Rtnn]
port number [ff]
firmware rev [ff]
switches [377]
maximum cylinder address 999.
maximum track address 99.
maximum sector address 99.

where t = M for RM02/RM03/RM05/RM80
P for RP06

This section should be run whenever there is any doubt as to the SC21/V1 or SC31 controller configuration or when inconsistent results are obtained in any other portion of the diagnostic. This section is not run by default and must be explicitly requested as follows:

DS> Start/SECTION:CONfiguration

The configuration section consists of the following test:

TEST 21 Get the controller configuration

3.5 DISTRIBUTION

The SC21/SC31 diagnostics are contained entirely on one floppy disk (Emulex part number VX9960501) or on one TU58 cassette (Emulex part number VX9960401), as appropriate to the system. The contents of this unit, which apply to the SC21/V1 or SC31 disk controller, are defined as follows:

ESC21.780	Command file to load the SC21/SC31 diagnostic and attach the controller to the VAX-11/780 system. This command file is invoked by typing "@ESC21.780" at the Diagnostic Supervisor (DS>) prompt symbol.
ESC21.750	Command file to load the SC21/SC31 diagnostic and attach the controller to the VAX-11/750 system. This command file is invoked by typing "@ESC21.750" at the DS> prompt symbol.
ESC21.730	Command file to load the SC21/SC31 diagnostic and attach the controller to the VAX-11/730 system. This command file is invoked by typing "@ESC21.730" at the DS> prompt symbol.
ESC21.EXE	The SC21/SC31 diagnostic program executable image.

ESC21.HLP The SC21/SC31 help file to provide the user with additional information on loading and running the diagnostics and its options. This file is obtained by typing "HELP ESC21 [subtopic]" at the DS> prompt symbol once the diagnostic medium is mounted in the appropriate drive.

The listings for the Emulex SC21/SC31 diagnostic program are identified as Emulex part number VX9960060. These listings contain the assembly list file (ESC21.LIS) and the link map file (ESC21.MAP) of the SC21/SC31 diagnostic.

NOTE

The listing files are proprietary information that belong to Emulex. They are released only with appropriate Software Source license.

3.6 MAINTENANCE HISTORY

Version 1.0 21 August 1981
 Diagnostic supervisor 6.0
 Initial release

Version 1.1 5 October 1981
 Diagnostic supervisor 6.2
 Change register names to conform to manual. Fix
 bug in format section that cleared register mask.
 Change format routine to be interrupt driven to
 help speed things up a bit.

Version 1.2 30 November 1981
 Diagnostic supervisor 6.2
 Set "FMT16" in RMOF to insure 32. sector mode. Change
 "RM_DO" to include unit number after error reset. Omit
 RMDB from test 1 initialized value check.

Version 1.3 1 June 1982
 Diagnostic supervisor 6.5
 Removed the maintenance function tests because of timing
 problems seen on the 11/780. Since these tests only
 check the maintenance mode firmware and not actual drive
 functionality, little or no diagnostic capability is
 lost by the removal of these tests. Added time stamps
 at start and completion of both firmware format and
 surface analysis functions. Changed Invalid command
 test and IVC bit test to wait for interrupt with
 embedded timer enabled instead of waiting for RDY bit to
 avoid possible infinite loop situation.

Version 1.4 29 June 1982
 Diagnostic supervisor 6.5
 Removed the last maintenance mode to do away with a
 problem in the IFL test seen only on units other than
 zero.

Version 1.5 28 July 1982

Diagnostic supervisor 6.5

Removed the format section since this is now done
through the Emulex disk formatting program, EDSKF.

Section 4 TC11 DIAGNOSTIC

4.1 GENERAL DESCRIPTION

This diagnostic test program is designed to aid in the acceptance testing, installation checkout, and corrective maintenance of the Emulex TC11 tape controller.

4.2 REQUIREMENTS

For proper program installation, the following hardware and software requirements should be observed.

4.2.1 HARDWARE REQUIREMENTS

The hardware necessary to properly run this diagnostic test consists of the following components: a VAX-11 processor with 128KW memory, a unibus adapter, a console device, an Emulex TC11 tape controller and at least one TC11-supported tape drive. It is assumed that the VAX CPU, memory and Unibus Adapter are known to be functioning properly.

4.2.2 SOFTWARE REQUIREMENTS

This program runs with the diagnostic supervisor ESSAA for the VAX-11/780 processor, ECSAA for the VAX-11/750 processor, or ENSAA for the VAX-11/730 processor, Version 6.0 or later.

4.3 LOADING PROCEDURES

The complete program loading requires three procedures.

4.3.1 LOADING PROCEDURES FOR THE VAX-11/780

To begin an Off-Line diagnostic session you must first bootstrap the DEC Diagnostic Supervisor. To accomplish this bootstrap, remove the floppy disk labeled "Local Console" from the drive and insert the DW780 channel diagnostic floppy disk, supplied by Digital Equipment Corporation (DEC), then enter the following instruction:

```
>>>P
>>>HALT
>>>BOOT
```

This instruction loads the Diagnostic Supervisor into memory which then announces itself with:

```
DIAGNOSTIC SUPERVISOR. ZZ-ESSAA-6.n-xxx
DS>
```

Remove the DEC DW780 channel diagnostic floppy disk and place the Emulex-supplied diagnostic floppy disk (Emulex part number VX9960501) in the drive. The diagnostic program must now be loaded and the TC11 device must be ATTached and SElected. There are three ways in which this procedure can be done: by using the Prompt mode, by using the Explicit (No Prompt) mode, or by using the Command File. Examples of each procedure are listed in Tables 4-1, 4-2, and 4-3. The underlined text indicates information which needs to be typed into the console by the user. It should follow the appropriate system prompt symbol which is a "DS>" or "?".

4.3.2 LOADING PROCEDURES FOR THE VAX-11/750

To begin an Off-Line diagnostic session, you must first bootstrap the DEC Diagnostic Supervisor. To accomplish this bootstrap, remove the TU58 cassette labeled "Local Console" from the drive, insert the DEC-supplied RH750/DW750 channel diagnostic cassette, place the bootstrap device select switch in the TU58 position, and press the RESET button. This procedure loads the Diagnostic Supervisor into memory which then announces itself with:

```
DIAGNOSTIC SUPERVISOR. ZZ-ECSAA-6.n-xxx
DS>
```

Remove the DEC RH750/DW750 channel diagnostic cassette and place the Emulex-supplied diagnostic cassette (Emulex part number VX9960401) in the drive. The diagnostic program must now be loaded and the TC11 device must be ATTached and SElected. There are three ways in which this procedure can be done: by using the Prompt mode, by using the Explicit (No Prompt) mode, or by using the Command File. Examples of each procedure are listed in Tables 4-1, 4-2, and 4-3. The underlined text indicates information which needs to be typed into the console by the user. It should follow the appropriate system prompt symbol which is a "DS>" or "?".

4.3.3 LOADING PROCEDURES FOR THE VAX-11/730

To begin an Off-Line diagnostic session, you must first bootstrap the DEC Diagnostic Supervisor. To accomplish this procedure, remove the TU58 cassette labeled "Local Console" from the Internal drive (unit 1) and insert the DEC-supplied "Load Path" diagnostic cassette (#37). Insert the Emulex diagnostic cassette (Emulex part number VX9960401) in the External drive (unit 0), and enter the following instruction:

```
>>>I
>>>L/P/S:FE00 DD1:ENSAA.EXE
>>>S 10000
```

This instruction loads the Diagnostic Supervisor into memory which then announces itself with:

```
DIAGNOSTIC SUPERVISOR. ZZ-ENSAA-6.n-xxx
DS>
```

The diagnostic program must now be loaded and the TC11 device must be ATTached and SElected. There are three ways in which this procedure can be done: by using the Prompt mode, by using the Explicit (No Prompt) mode, or by using the Command File. Examples of each procedure are listed in Tables 4-1, 4-2, and 4-3. The underlined text indicates information which needs to be typed into the console by the user. It should follow the appropriate system prompt symbol which is a "DS>" or "?".

Table 4-1. Prompt Mode

VAX-11/780	VAX-11/750	VAX-11/730
DS> <u>LOAD ETC11</u> DS> <u>ATTACH</u> DEVICE TYPE ? <u>DW780</u> DEVICE LINK ? <u>SBI</u> DEVICE NAME ? <u>DW0</u> <u>TR ? 3</u> <u>BR ? 4</u> DS> <u>ATTACH</u> DEVICE TYPE ? <u>TC11</u> DEVICE LINK ? <u>DW0</u> DEVICE NAME ? <u>TCA</u> CSR ? <u>772520</u> DS> <u>SELECT TCA</u>	DS> <u>LOAD ETC11</u> DS> <u>ATTACH</u> DEVICE TYPE ? <u>DW750</u> DEVICE LINK ? <u>CMI</u> DEVICE NAME ? <u>DW0</u> DS> <u>ATTACH</u> DEVICE TYPE ? <u>TC11</u> DEVICE LINK ? <u>DW0</u> DEVICE NAME ? <u>TCA</u> CSR ? <u>772520</u> DS> <u>SELECT TCA</u>	DS> <u>LOAD ETC11</u> DS> <u>ATTACH</u> DEVICE TYPE ? <u>DW730</u> DEVICE LINK ? <u>HUB</u> DEVICE NAME ? <u>DW0</u> DS> <u>ATTACH</u> DEVICE TYPE ? <u>TC11</u> DEVICE LINK ? <u>DW0</u> DEVICE NAME ? <u>TCA</u> CSR ? <u>772520</u> DS> <u>SELECT TCA</u>

Table 4-2. Explicit Mode

VAX-11/780	VAX-11/750
DS> <u>LOAD ETC11</u> DS> <u>ATT DW780 SBI DW0 3 4</u> DS> <u>ATT TC11 DW0 TCA 772520</u> DS> <u>SEL TCA</u>	DS> <u>LOAD ETC11</u> DS> <u>ATT DW750 CMI DW0</u> DS> <u>ATT TC11 DW0 TCA 772520</u> DS> <u>SEL TCA</u>
VAX-11/730	
<u>DS> LOAD ETC11</u> <u>DS> ATT DW730 HUB DW0</u> <u>DS> ATT TC11 DW0 TCA 772520</u> <u>DS> SEL TCA</u>	

Table 4-3. Command File

VAX-11/780	VAX-11/750
<pre> DS> @ETC11.780 DS> LOAD ESC21 DS> ATT DW780 SBI DW0 3 4 DS> ATT TC11 DW0 TCA 772520 DS> SELECT TCA </pre>	<pre> DS> @ETC11.750 DS> LOAD ESC21 DS> ATT DW750 CMI DW0 DS> ATT TC11 DW0 TCA 772520 DS> SELECT TCA </pre>
<hr/> <p style="text-align: center;">VAX-11/730</p> <hr/> <pre> DS> @ETC11.730 DS> LOAD ETC11 DS> ATT DW730 HUB DW0 DS> ATT TC11 DW0 TCA 772520 DS> SEL TCA </pre> <hr/>	

Once the Unit Under Test (UUT) has been SELECTed, the diagnostic program must be started as follows:

```
DS> Start[/((switches))]
```

See the VAX Diagnostic User's Guide, DEC part number EK-VX11D-UG, for the description of the available switches.

4.4 PROGRAM DESCRIPTION

This program contains 27 tests which check the TC11 tape controller. These tests are further divided into five sections: Default, Configuration, phase encoded (PE), Tape, and Manual. When the program is first started, it responds with:

```

..program: Emulex TC11 Tape Controller Diagnostic, Rev n.n
Testing: _TC
Enter drive number to test [(0), 0-3] :

```

4.4.1 DEFAULT SECTION

This section checks the basic TC11 controller functions such as register read/write, correct error detection, controller initialization, and bus address checks. This section is run by default if no section name is specified in the Start command. This section may be run without any tape loaded or without any drive on line, since no tape motion is generated by any of these tests. The default section consists of the following tests:

Test	1:	Address all registers
Test	2:	MTBRC register (all 1 & 0)
Test	3:	MTBRC register (moving 1 & 0)
Test	4:	MTCMA register (all 1 & 0)
Test	5:	MTCMA register (moving 1 & 0)
Test	6:	MTD register (all 1 & 0)
Test	7:	MTD register (moving 1 & 0)
Test	8:	Check unit select bits
Test	9:	Check IE
Test	10:	Check A16 & A17 increment
Test	11:	Check byte loading of command register
Test	12:	Check density bits

4.4.2 CONFIGURATION SECTION

This section is used to display the Emulex TC11 controller configuration. The information is displayed in the following format:

```
Emulex TC11 Tape Controller CSR [177777]
vector [377] is 800(NRZI)/1600(PE)].
Unit 0 responded [NOT] ready, [NOT] at BOT, [NOT] write locked
Unit 1 responded [NOT] ready, [NOT] at BOT, [NOT] write locked
Unit 2 responded [NOT] ready, [NOT] at BOT, [NOT] write locked
Unit 3 responded [NOT] ready, [NOT] at BOT, [NOT] write locked
```

This section should be run at installation time or any time inconsistent results are obtained in any other portion of the diagnostic. This section is not run by default and must be explicitly requested as follows:

```
DS> StArt/SEctIon:CONfiguration
```

The configuration section consists of the following test:

```
Test 13: Get controller configuration
```

4.4.3 PE SECTION

This section is used to execute the built-in diagnostics of the PE printed circuit board assembly (PCBA). This self-test consists of a simulated phase-encoded record that contains a preamble, 20 identical data characters, and a shortened postamble. This section can not be run if the PE option is not installed. The PE section consists of the following test:

```
Test 14: Execute internal PE test
```

This section is not run by default and must be explicitly requested as follows:

```
DS> StArt/SEctIon:PE
```

4.4.4 TAPE SECTION

This section is used by the operator to execute tape motion on the drive to check tape transport operation. The tests in this section check for Beginning of Tape (BOT), End of Tape (EOT), Write and Read functions as well as Rewind, Space Forward, and Space Reverse functions. The use of this section requires a scratch tape (recommended 600 ft) be mounted in the drive, and that the drive be in the On-Line mode.

NOTE

This section tests tape transport motion only, and is not intended to check data reliability. Once started, this section should cycle through to completion. Some of the tests assume the previous tests have been done and results of explicitly running these tests out of order are not specified.

This section is not run by default and must be explicitly requested as follows:

DS> STart/SEctIon:Tape

The tape section consists of the followings tests:

Test	15:	Check for BOT
Test	16:	Check Rewind function
Test	17:	Check Write function
Test	18:	Check Read function
Test	19:	Check Write EOF function
Test	20:	Check Space Forward/Reverse function
Test	21:	Check Rewind & Backspace ignored at BOT
Test	22:	Check that NXM bit can set
Test	23:	Check Rewind causes two interrupts
Test	24:	Data transfer test
Test	25:	Tape positioning test

4.4.5 MANUAL SECTION

The manual section contains two tests which check for EOT and for proper operation of the Off-Line function. This section contains the following tests:

Test	26:	Check for EOT
Test	27:	Check off-line function

This section is not run by default and must be explicitly requested as follows:

DS> STart/SEctIon:MANual

4.5 ERROR AND INFORMATION MESSAGES

The TC11 diagnostic may output a number of different messages for information purposes or for announcing error conditions that are detected during execution of the diagnostics. These messages can be any one of the four following types:

- 1) Error messages output to indicate something did not occur as expected but testing is to continue.
- 2) System fatal errors which indicate something catastrophic has occurred and continued testing is pointless. The occurrence of one of these errors terminates the diagnostic.
- 3) Information messages such as reporting the configuration of the controller or listing the function being tested in the current test.
- 4) Operator interaction requested such as entry of the unit to test by the operator.

4.6 DISTRIBUTION

The TC11 diagnostics are contained entirely on one floppy disk (Emulex part number VX9960501) or on one TU58 cassette (Emulex part number VX9960401), as appropriate to the system. The contents of this unit which apply to the TC11 are defined as follows:

ETC11.780	Command file to load the TC11 diagnostic and attach the TC11 controller to the VAX-11/780 system. This command file is invoked by typing "@ETC11.780" at the diagnostic supervisor (DS>) prompt symbol..
ETC11.750	Command file to load the TC11 diagnostic and attach the TC11 controller to the VAX-11/750 system. This command file is invoked by typing "@ETC11.750" at the DS> prompt symbol..
ETC11.730	Command file to load the TC11 diagnostic and attach the TC11 controller to the VAX-11/730 system. This command file is invoked by typing "@ETC11.730" at the DS> prompt symbol.
ETC11.EXE	The TC11 diagnostic program executable image.
ETC11.HLP	The TC11 help file to provide the user with additional information on loading and running the diagnostics and its options. This file is obtained by typing "HELP ETC11 [subtopic]" at the DS> prompt symbol once the diagnostic medium is mounted in the appropriate drive.

The listings for the Emulex TC11 diagnostic program are identified as Emulex part number VX9960040. These listings contain the assembly list file (ETC11.LIS) and the link map file (ETC11.MAP) of the TC11 Diagnostic.

NOTE

The listing files are proprietary information that belong to Emulex. They are released only with appropriate Software Source license.

4.7 MAINTENANCE HISTORY

Version 1.0 4 June 1982
 Diagnostic Supervisor 6.0
 Initial release

Version 1.1 17 Dec 1982
 Diagnostic Supervisor 6.0
 Added optional address support for new PCBA.

Section 5 CS11 DIAGNOSTICS

5.1 GENERAL DESCRIPTION

This diagnostic test program is designed to aid in the acceptance testing, installation checkout, and corrective maintenance of the Emulex CS11 Communications Multiplexer with one to four CP11 distribution panels.

5.2 REQUIREMENTS

For proper program installation, the following hardware and software requirements should be observed.

5.2.1 HARDWARE REQUIREMENTS

The hardware necessary to properly run this diagnostic test consists of the following components: a VAX-11 processor with 128KW memory, a Unibus adaptor, a console device, an Emulex CS11 Communications Multiplexer, one to four CP11 distribution panels, one to eight adaptor panels, and one to 64 Digital Equipment Corporation (DEC) type H315 wrap-around test connectors. It is assumed that the VAX CPU, memory, and Unibus adaptor are known to be functioning properly.

5.2.2 SOFTWARE REQUIREMENTS

This program runs with the diagnostic supervisor ESSAA for the VAX-11/780 processor, ECSAA for the VAX-11/750 processor, or ENSAA for the VAX-11/730 processor, Version 6.0 or later.

5.3 LOADING PROCEDURES

The complete program loading procedure requires three operations.

5.3.1 LOADING PROCEDURES FOR THE VAX-11/780

To begin an Off-Line diagnostic session, you must first bootstrap the DEC Diagnostic Supervisor. To accomplish this procedure, remove the floppy disk labeled "Local Console" from the drive and insert the DEC-supplied DW780 channel diagnostic floppy disk, then enter the following instruction:

```
>>>^P
>>>HALT
>>>BOOT
```

This instruction loads the Diagnostic Supervisor into memory which then announces itself with:

DIAGNOSTIC SUPERVISOR. ZZ-ESSAA-6.n-xxx
DS>

Remove the DEC DW780 channel diagnostic floppy disk and place the Emulex-supplied diagnostic floppy disk (Emulex part number VX9960501) in the drive. The diagnostic program must now be loaded and the CS11/CS21 device must be ATTached and SElected. There are three ways in which this procedure can be done: by using the Prompt mode, by using the Explicit (No Prompt) mode, or by using the Command File. Examples of each procedure are listed in Tables 5-1, 5-2, and 5-3. The underlined text indicates information which needs to be typed into the console by the user. It should follow the appropriate system prompt symbol which is a "DS>" or "?".

5.3.2 LOADING PROCEDURES FOR THE VAX-11/750

To begin an Off-Line diagnostic session, you must first bootstrap the DEC Diagnostic Supervisor. To accomplish this procedure, remove the TU58 cassette labeled "Local Console" from the drive, insert the DEC-supplied RH750/DW750 channel diagnostic cassette, place the bootstrap device select switch in the TU58 position, and press the RESET button. This procedure loads the Diagnostic Supervisor into memory which then announces itself with:

DIAGNOSTIC SUPERVISOR. ZZ-ECSAA-6.n-xxx
DS>

Remove the DEC RH750/DW750 channel diagnostic cassette and place the Emulex-supplied diagnostic cassette (Emulex part number VX9960401) in the drive. The diagnostic program must now be loaded and the CS11/CS21 device must be ATTached and SElected. There are three ways in which this procedure can be done: by using the Prompt mode, by using the Explicit (No Prompt) mode, or by using the Command File. Examples of each procedure are listed in Tables 5-1, 5-2, and 5-3. The underlined text indicates information which needs to be typed into the console by the user. It should follow the appropriate system prompt symbol which is a "DS>" or "?".

5.3.3 LOADING PROCEDURES FOR THE VAX-11/730

To begin an Off-Line diagnostic session, you must first bootstrap the DEC Diagnostic Supervisor. To accomplish this procedure, remove the TU58 cassette labeled "Local Console" from the Internal drive (unit 1), and insert the DEC-supplied "Load Path" diagnostic cassette (#37), then insert the Emulex diagnostic cassette (Emulex part number VX9960401) in the External drive (unit 0), and enter the following instruction:

```
>>>I  
>>>L/P/S:FE00 DDL:ENSAA.EXE  
>>>S_10000
```

This instruction loads the Diagnostic Supervisor into memory which then announces itself with:

DIAGNOSTIC SUPERVISOR. ZZ-ENSAA-6.n-xxx
DS>

The diagnostic program must now be loaded and the CS11/CS21 device must be ATTached and SElected. There are three ways in which this procedure can be done: by using the Prompt mode, by using the Explicit (No Prompt) mode, or by using the Command File. Examples of each procedure are listed in Tables 5-1, 5-2, and 5-3. The underlined text indicates information which needs to be typed into the console by the user. It should follow the appropriate system prompt symbol which is a "DS>" or "?".

Table 5-1. Prompt Mode

VAX-11/780	VAX-11/750	VAX-11/730
DS> <u>LOAD ECS11</u> DS> <u>ATTACH</u> DEVICE TYPE ? <u>DW780</u> DEVICE LINK ? <u>SBI</u> DEVICE NAME ? <u>DW0</u> TR ? <u>3</u> BR ? <u>4</u> DS> <u>ATTACH</u> DEVICE TYPE ? <u>DH</u> DEVICE LINK ? <u>DW0</u> DEVICE NAME ? <u>DHA</u> CSR ? <u>760020</u> BR ? <u>5</u> DS> <u>SELECT DHA</u> DS> <u>ATTACH</u> DEVICE TYPE ? <u>DM</u> DEVICE LINK ? <u>DW0</u> DEVICE NAME ? <u>DMA</u> CSR ? <u>770500</u> BR ? <u>4</u> DS> <u>SELECT DMA</u> DS> <u>SET TRACE</u>	DS> <u>LOAD ECS11</u> DS> <u>ATTACH</u> DEVICE TYPE ? <u>DW750</u> DEVICE LINK ? <u>CMI</u> DEVICE NAME ? <u>DW0</u> DS> <u>ATTACH</u> DEVICE TYPE ? <u>DH</u> DEVICE LINK ? <u>DW0</u> DEVICE NAME ? <u>DHA</u> CSR ? <u>760020</u> BR ? <u>5</u> DS> <u>SELECT DHA</u> DS> <u>ATTACH</u> DEVICE TYPE ? <u>DM</u> DEVICE LINK ? <u>DW0</u> DEVICE NAME ? <u>DMA</u> CSR ? <u>770500</u> BR ? <u>4</u> DS> <u>SELECT DMA</u> DS> <u>SET TRACE</u>	DS> <u>LOAD ECS11</u> DS> <u>ATTATCH</u> DEVICE TYPE ? <u>DW730</u> DEVICE LINK ? <u>HUB</u> DEVICE NAME ? <u>DW0</u> DS> <u>ATTATCH</u> DEVICE TYPE ? <u>DH</u> DEVICE LINK ? <u>DW0</u> DEVICE NAME ? <u>DHA</u> CSR ? <u>760020</u> BR ? <u>5</u> DS> <u>SELECT DHA</u> DS> <u>ATTACH</u> DEVICE TYPE ? <u>DM</u> DEVICE LINK ? <u>DW0</u> DEVICE NAME ? <u>DMA</u> CSR ? <u>770500</u> BR ? <u>4</u> DS> <u>SELECT DMA</u> DS> <u>SET TRACE</u>

NOTE

Continue the above steps, changing the CSR and device name to DHB, DHC, etc., or DMB, DMC, etc. for each additional CP11 panel to be tested. Each CP11 panel is described as an individual logical unit for testing purposes.

Table 5-2. Explicit Mode

VAX-11/780	VAX-11/750
DS> <u>LOAD ECS11</u> DS> <u>ATT DW780 SBI DW0 3 4</u> DS> <u>ATT DH DW0 DHA 760020 5</u> DS> <u>ATT DM DW0 DMA 770500 4</u> DS> <u>ATT DH DW0 DHB 760040 5</u> DS> <u>ATT DM DW0 DMB 770520 4</u> DS> <u>ATT DH DW0 DHC 760060 5</u> DS> <u>ATT DM DW0 DMC 770540 4</u> DS> <u>ATT DH DW0 DHD 760100 5</u> DS> <u>ATT DM DW0 DMD 770560 4</u> DS> <u>SEL DHA</u> DS> <u>SEL DMA</u> DS> <u>SEL DHB</u> DS> <u>SEL DMB</u> DS> <u>SEL DHC</u> DS> <u>SEL DMC</u> DS> <u>SEL DHD</u> DS> <u>SEL DMD</u> DS> <u>SET TRACE</u>	DS> <u>LOAD ECS11</u> DS> <u>ATT DW750 CMI DW0</u> DS> <u>ATT DH DW0 DHA 760020 5</u> DS> <u>ATT DM DW0 DMA 770500 4</u> DS> <u>ATT DH DW0 DHB 760040 5</u> DS> <u>ATT DM DW0 DMB 770520 4</u> DS> <u>ATT DH DW0 DHC 760060 5</u> DS> <u>ATT DM DW0 DMC 770540 4</u> DS> <u>ATT DH DW0 DHD 760100 5</u> DS> <u>ATT DM DW0 DMD 770560 4</u> DS> <u>SEL DHA</u> DS> <u>SEL DMA</u> DS> <u>SEL DHB</u> DS> <u>SEL DMB</u> DS> <u>SEL DHC</u> DS> <u>SEL DMC</u> DS> <u>SEL DHD</u> DS> <u>SEL DMD</u> DS> <u>SET TRACE</u>
VAX-11/730	
DS> <u>LOAD ECS11</u> DS> <u>ATT DW730 HUB DW0</u> DS> <u>ATT DH DW0 DHA 760020 5</u> DS> <u>ATT DM DW0 DMA 770500 4</u> DS> <u>ATT DH DW0 DHB 760040 5</u> DS> <u>ATT DM DW0 DMB 770520 4</u> DS> <u>ATT DH DW0 DHC 760060 5</u> DS> <u>ATT DM DW0 DMC 770540 4</u> DS> <u>ATT DH DW0 DHD 760100 5</u> DS> <u>ATT DM DW0 DMD 770560 4</u> DS> <u>SEL DHA</u> DS> <u>SEL DMA</u> DS> <u>SEL DHB</u> DS> <u>SEL DMB</u> DS> <u>SEL DHC</u> DS> <u>SEL DMC</u> DS> <u>SEL DHD</u> DS> <u>SEL DMD</u> DS> <u>SET TRACE</u>	

Table 5-3. Command File

VAX-11/780	VAX-11/750
<pre> DS> @ECS11.780 DS> ATT DW780 SBI DW0 3 4 DS> ATT DH DW0 DHA 760020 5 DS> ATT DM DW0 DMA 770500 4 DS> ATT DH DW0 DHB 760040 5 DS> ATT DM DW0 DMB 770520 4 DS> ATT DH DW0 DHC 760060 5 DS> ATT DM DW0 DMC 770540 4 DS> ATT DH DW0 DHD 760100 5 DS> ATT DM DW0 DMD 770560 4 DS> SEL DHA DS> SEL DMA DS> SEL DHB DS> SEL DMB DS> SEL DHC DS> SEL DMC DS> SEL DHD DS> SEL DMD DS> SET TRACE </pre>	<pre> DS> @ECS11.750 DS> ATT DW750 CMI DW0 DS> ATT DH DW0 DHA 760020 5 DS> ATT DM DW0 DMA 770500 4 DS> ATT DH DW0 DHB 760040 5 DS> ATT DM DW0 DMB 770520 4 DS> ATT DH DW0 DHC 760060 5 DS> ATT DM DW0 DMC 770540 4 DS> ATT DH DW0 DHD 760100 5 DS> ATT DM DW0 DMD 770560 4 DS> SEL DHA DS> SEL DMA DS> SEL DHB DS> SEL DMB DS> SEL DHC DS> SEL DMC DS> SEL DHD DS> SEL DMD DS> SET TRACE </pre>
<p>VAX-11/730</p> <hr/> <pre> DS> @ECS11.730 DS> ATT DW730 HUB DW0 DS> ATT DH DW0 DHA 760020 5 DS> ATT DM DW0 DMA 770500 4 DS> ATT DH DW0 DHB 760040 5 DS> ATT DM DW0 DMB 770520 4 DS> ATT DH DW0 DHC 760060 5 DS> ATT DM DW0 DMC 770540 4 DS> ATT DH DW0 DHD 760100 5 DS> ATT DM DW0 DMD 770560 4 DS> SEL DHA DS> SEL DMA DS> SEL DHB DS> SEL DMB DS> SEL DHC DS> SEL DMC DS> SEL DHD DS> SEL DMD DS> SET TRACE </pre> <hr/>	

NOTE

The Command File is set up to ATTACH four CP11 panels, with base addresses of 760020 and 770500 for the first DH and DM devices, respectively. If the CS11 is configured to access other addresses, use either Explicit mode or Prompt mode to ATTACH and run the diagnostic, or edit the Command File to the desired address.

Once the UUT has been ATTACHed and SELECTed, the diagnostic must be started as follows:

```
DS> ST(art)[/(SWITCHES)]
```

See the VAX Diagnostic User's Guide for the description of the available switches.

5.4 PROGRAM DESCRIPTION

This program contains 29 tests which check the CS11 Communications Multiplexer controller and the integral DM11 modem control unit. These tests are further divided into four sections: configuration, default, silo and modem. When the program is first started it responds with:

..program: Emulex CS11/CS21 Multiplexer Diagnostic, Rev N.N

Testing: _DHA _DMA (_DHB, _DMB, _DHC, _DMC, _DHD, _DMD)

Lines currently selected for test:

Panel Number	Line Mask	Line Number(s)
0	FFFF(X)	15,14,13,12,11,10,9,8,7,6,5,4,3,2,1,0
1	0000(X)	
2	0000(X)	
3	0000(X)	

Change selected lines [(no), yes]

Local loopback enabled [(yes), no]

NOTE

In this configuration, the program is set up to test only one panel. The default is to check all 16 lines on the one panel, but this check can be changed by answering "Y" to the "Change selected lines" question. The line selection mask is specified in hexadecimal format and the bits in this mask are defined from left-to-right in descending order, while lines on the CP11 distribution panel are defined from left-to-right in ascending order. Each line which is in the line selection mask, and which is selected for testing, requires a DEC-type H315 wrap-around test connector, unless the local loopback is selected.

5.4.1 DEFAULT SECTION

This section checks the basic CS11 controller functions such as register read/write, correct error detection, maintenance mode features, controller initialization, and bus address checks. This section is run by default if no section name is specified in the Start command. The default section consists of the following tests:

Test	1:	ADDRESS ALL DH REGISTERS
Test	2:	ADDRESS ALL DM REGISTERS
Tset	3:	LPR REGISTER (MOVING 1 & 0)
Test	4:	CAR REGISTER (ALL 1 & 0)
Test	5:	CAR REGISTER MOVING 1 & 0)
Test	6:	CAR MEMORY ADDRESSING TEST
Test	7:	BCR REGISTER (ALL 1 & 0)
Test	8:	BCR REGISTER (MOVING 1 & 0)
Test	9:	BCR MEMORY ADDRESSING TEST
Test	10:	BKR REGISTER (MOVING 1 & 0)
Test	11:	CHECK EA BITS
Test	12:	TRANSMITTER TIMING TEST
Test	13:	RECEIVER TIMING TEST
Test	14:	BASIC DATA TEST
Test	15:	SINGLE LINE DATA TEST
Test	16:	BASIC PARITY LOGIC TEST
Test	17:	SINGLE LINE AUTO ECHO TEST
Test	18:	BREAK BIT TEST
Test	19:	CHECK THAT OVERRUN SETS
Test	20:	MULTI-LINE AUTO ECHO TEST
Test	21:	AUTO ECHO TEST, ALL SELECTED LINES

5.4.2 SILO SECTION

This section tests the silo status register for correct operation by filling the silo with test characters or trying to remove a specified number of characters from the filled silo.

NOTE

This section cannot be run with the Extended Silo feature enabled (bit 01 of SW1) because the silo maintenance bit is included as part of the silo fill level in the Extended Silo mode.

This section is not run by default and must be explicitly requested as follows:

ST(art)/SEC(tion):SILO

The silo section consists of the following tests:

Test 22: CHECK THAT SSR COUNTS UP
Test 23: CHECK THAT SSR COUNTS DOWN
Test 24: TESTS SILO ALARM LEVEL

5.4.3 MODEM SECTION

This section checks the modem signals. It is not run by default and must be explicitly requested as follows:

ST(art)/SEC(tion):MODEM

The modem section consists of the following tests:

Test 25: CHECK LINE ENABLE BIT
Test 26: CHECK CLEAR TO SEND AND CARRIER
Test 27: CHECK RING
Test 28: CHECK SECONDARY RECEIVE

5.4.4 CONFIGURATION SECTION

This section should be run as part of the controller installation as well as any time that the CS11/21 diagnostics are run. This test helps to determine the controller configuration. The following information is provided by this test:

Test 29: DISPLAY CONTROLLER CONFIGURATION

Emulex CS11/21 Communications Multiplexer has the extended silo enabled [disabled]

PANEL	LUN	DH CSR	DH VECTOR	DM CSR	DM VECTOR
0	0	777777	777(R)		
0	0	777777	777(T)		
0	1			777777	777
1	2	777777	777(R)		
1	2	777777	777(T)		
1	3			777777	777
2	4	777777	777(R)		
2	4	777777	777(T)		
2	5			777777	777
3	6	777777	777(R)		
3	6	777777	777(T)		
3	7			777777	777

This section is not run by default and must be explicitly requested as follows:

ST(art)/SEC(tion):CON(figuration)

5.5 DISTRIBUTION

The CS11/CS21 diagnostics are contained entirely on one floppy disk (Emulex part number VX9960501), or on one cassette (Emulex part number VX9960401), as appropriate to the system. The contents of this unit which apply to the CS11 or CS21 are defined as follows:

ECS11.780	Command File to load the CS11/CS21 diagnostic and attach the CS11 controller to the VAX-11/780 system. This Command File is invoked by typing "@ECS11.780" after the diagnostic supervisor (DS>) prompt symbol.
ECS11.730	Command File to load the CS11/CS21 diagnostic and attach the CS11 controller to the VAX-11/730 system. This Command File is invoked by typing "@ECS11.730" after the DS> prompt symbol.

ECS21.780	Command File to load the CS11/CS21 diagnostic and attach the CS21 controller to the VAX-11/780 system. This Command File is invoked by typing "@ECS21.780" after the DS> prompt symbol.
ECS21.750	Command File to load the CS11/CS21 diagnostic and attach the CS21 controller to the VAX-11/750 system. This Command File is invoked by typing "@ECS21.750" after the DS> prompt symbol.
ECS21.730	Command File to load the CS11/CS21 diagnostic and attach the CS21 controller to the VAX-11/730 system. This Command File is invoked by typing "@ECS21.730" after the DS> prompt symbol.
ECS11.EXE	The CS11/CS21 diagnostic program executable image.
ECS11.HELP	The CS11/CS21 HELP file to provide the user with additional information on loading and running the diagnostic and it's options. This file is obtained by typing "HELP ECS11 [subtopic]" at the DS> prompt symbol once the CS11 diagnostic medium is mounted in the appropriate drive.

The listings for the Emulex CS11/CS21 diagnostic program are identified as Emulex part number VX9960020. These listings contain the assembly file (ECS11.LIS) and the link map file (ECS11.MAP) of the CS11/CS21 diagnostic.

NOTE

The listing files are proprietary information that belong to Emulex. They are released only with appropriate Software Source license.

5.6 MAINTENANCE HISTORY

Version 1.0 4 December 1981
 Diagnostic supervisor 6.0
 Initial release

Version 1.1 4 June 1982
 Diagnostic supervisor 6.5
 Added local loopback option so the diagnostic could run without the turnaround connectors.
 Added configuration section.
 Changes to make the diagnostic work effectively on the VAX-11/780.



Reader's Comments

Your comments and suggestions will help us in our continuous effort to improve the quality and usefulness of our publication.

Manual Part Number _____ Rev. _____

What is your general reaction to this manual? In your judgment is it complete, accurate, well organized, well written, etc.? Is it easy to use? _____

What features are most useful? _____

What faults or errors have you found in the manual? _____

Does this manual satisfy the need you think it was intended to satisfy? _____

Does it satisfy *your* needs? _____ Why? _____

☐ Please send me the current copy of the *Controller Handbook*, which contains the information on the remainder of EMULEX's controller products.

Name _____

Street _____

Title _____

City _____

Company _____

State/Country _____

Department _____

Zip _____

Additional copies of this document are available from:

Emulex Corporation
3545 Harbor Boulevard
P.O. Box 6725
Costa Mesa, CA 92626
Attention: Customer Services

Fold Here and Staple

Do Not Tear — Fold Here



NO POSTAGE
NECESSARY
IF MAILED
IN THE
UNITED STATES

BUSINESS REPLY MAIL

FIRST CLASS PERMIT NO. 202 COSTA MESA CA

POSTAGE WILL BE PAID BY ADDRESSEE

EMULEX CORPORATION
3545 HARBOR BOULEVARD
P.O. BOX 6725
COSTA MESA, CALIFORNIA 92626
ATTN: TECHNICAL PUBLICATIONS

